






Click download to down the installed file:




Access the folder containing the installation file, right-click and select Run As Administrator to perform the installation process.




There are 3 options:


Basic:




Custom:



Download Media:




Click Download, the installation file download process is started, this process takes a few minutes depending on the Internet connection speed




After the download is complete, you will have the SQLEXPADV_x64_ENU.exe file, this file is used to install Microsoft SQL Server 2019 Express on any desktop or laptop running Windows 10,11 or below and medium servers running Windows Server 2016/2019. .

The process to install Microsoft SQL Server 2019 Express is as follows:


Right click on the file SQLEXPADV_x64_ENU.exe, select run as Administrator, Select Yes if there is a screen asking "Do you want to allow this app to make changes to your device".




Select the path to extract the installation files, here is the default. Click OK and the decompression process will begin.




After decompressing, the installation screen will appear as follows:





Click New SQL Server stand-alone installation or add feature to an existing installation, the following screen will appear:




Click Next




Click Next



Click Next



Click to select the options you want to install. In Microsoft SQL Server 2017/2019 version, Microsoft supports Machine Learning that integrates data analysis with R, Python and Java programming languages.




Click Next to continue.

You can choose Default instance if you are installing Microsoft SQL Server 2019 Express or any other version for the first time. To access the Database, just select (local) or the name of the computer.


Named instance, can be named as desired by the database administrator. To access the Database, you must add the instance name, for example here is (local)\SQL2019E or (PC Name)\SQL2019E

Click Next to continue




If you chose the Java language to support Machine Learning in the previous step, you will be asked to install Open JRE or just the path of the JRE version installed on your computer.


Click Next




Click Next




Click Next




Click Accept to install Microsoft R Open if you selected R in the Machine Learning section in the previous step..




Click Next




Click Accept to install Python if you chose R in the Machine Learning section in the previous step




Click Next.




This installation takes a few minutes to complete.




Click OK và click Close




Continue to Install SQL Server Management Tools, click Install SQL Server Management Tools to open the Web link to download SQL Server Management Studio




Continue right-clicking on the newly downloaded file (usually named SSMS-Setup-ENU.exe) and select Run As Administrator to install SQL Server Management Tools. Select Yes if asked "Do you want to allow this app to make changes to your device?"



Click Install



After installation, it will ask to restart the computer.



You can click Close to close and restart the machine later.